# MTD2A timer

MTD2A: Model Train Detection And Action – arduino library <a href="https://github.com/MTD2A/MTD2A">https://github.com/MTD2A/MTD2A</a>
Jørgen Bo Madsen / V1.1 / 08-10-2025

MTD2A\_timer is an easy-to-use, advanced and functional C++ class for non-blocking time control. MTD2A supports parallel processing and asynchronous execution.

The class is among a number of logical building blocks that solve different functions.

#### Common to all building blocks are:

- They support a wide range of input sensors and output devices
- Are simple to use to build complex solutions with few commands
- They operate non-blocking, process-oriented and state-driven
- Offers extensive control and troubleshooting information
- Thoroughly documented with examples

## Table of contents

Feature Description	MTD2A_binary_input	1
Process phases	<del> </del>	
Set and Get Features Overview	·	
Print_conf();		
<del>-</del> "		
	Precise timing	

### **Feature Description**

MTD2A\_binary\_input process consists of 3 functions:

- MTD2A timer object name ("object name", CountDownMS);
- 2. object\_name.timer ( { RESET\_TIMER | START\_TIMER | PAUSE\_TIMER | STOP\_TIMER }, countDownMS} );
  Called in void setup ();
- 3. MTD2A\_loop\_execute (); Called as the last instruction in void loop ();

The first argument uses the default value and the function can be called with none and up to 2 arguments.

```
MTD2A_timer object_name ();
MTD2A_timer object_name ("Object_name");
MTD2A_timer object_name ("Object_name", countDownMS);
Default: ("Object_name", 0 );
```

#### Eksempel


More examples and youtube demo video:

https://github.com/MTD2A/MTD2A/tree/main/examples

DEMO video: <a href="https://youtu.be/UU4k4\_8GWfM">https://youtu.be/UU4k4\_8GWfM</a>

### **Process phases**

Depending on the current configuration, the process is carried out in between 2 and multiple phases with pauses.



- 3. The initial phase when the program starts STOP\_TIMER.
- 0. When function <a href="https://object\_name.timer">object\_name.timer</a> (RESET\_TIMER); Is called. Can occur at any time.
- 1. When function object\_name.timer (START\_TIMER); Is called. May occur several times after each pause.
- 2. When function object\_name.timer (PAUSE\_TIMER); Is called. May occur several times after start and reset.
- 3. When function object\_name.timer (STOP\_TIMER); Is called or when the time has expired. countDownMS = 0.

#### **Global Number Constants:**

```
RESET_TIMER<mark>, START_TIMER, PAUSE_TIMER og STOP_TIMER</mark>
```

The immediate phase shift can be identified by function: <a href="mailto:object\_name.get\_phaseChange">object\_name.get\_phaseChange</a> (); = { true | false }

#### **Proces status**

```
When transitioning to START_TIMER or RESET_TIMER, ProcessState switches to ACTIVE. When transitioning to STOP_TIMER, the processState switches to COMPLETE.

ProcessState remains ACTIVE during PAUSE_TIMER.
```

#### **Timing**

The time period can be set when the object is instantiated. Subsequently, new time periods can be defined with the functin: <a href="mailto:object\_name.set\_countDownMS">object\_name.set\_countDownMS</a> ({0 - 4294967295}); But only when processState is COMPLETE

Refer to the document MTD2A.PDF and the section "Cadence", "Synchronization" and "Execution speed".

# Set and Get Features Overview

Set functions	Comment
set_countDownMS ( {0 - 4294967295} );	Set new count down time in milliseconds
set_debugPrint ( {ENABLE   DISABLE} );	Activate print phase number and text.
set_errorPrint ( {ENABLE   DISABLE} );	Activate error messages.

Get functions	Comment
get_processtState (); return bool {ACTIVE   COMPLETE}	Process state
get_phaseChange (); return bool {true   false}	Momentarily phase change (one loop time)
	RESET_TIMER = 0, START_TIMER =1,
get_phaseNumber (); return uint8_t {0 - 3}	PAUSE_TIMER = 2, STOP_TIMER = 3
get_startTimeMS (); return uint32_t milliseconds	Last START_TIMER
get_stopTimeMS (); return uint32_t milliseconds	STOP_TIMER or countDownMS is zero
get_pauseTimeMS (); return uint32_t milliseconds	Acuumulated pause time (sum of all pause
	periods). Zero if no pause initiated
get_remainTimeMS (); return uint32_t milliseconds	Remining time since first start
get_elapsedTimeMS (); return uint32_t milliseconds	elapsed time since first start
act react crear (), return vint0 t (0.3EE)	Get error/warning number and reset
get_reset_error (); return uint8_t {0-255}	number: Error [1 – 127] warning [128 – 255]

Operator overloading	Function
object_name_1 == object_name_2	bool processState_1 == processState_2
object_name_1 != object_name_2	bool processState_1 != processState_2
object_name_1 > object_name_2	bool processState_1 = ACTIVE & processState_2 = COMPLETE
object_name_1 < object_name_2	bool processState_1 = COMPLETE & processState_2 = ACTIVE
object_name_1 >> object_name_2	bool stopTimeMS_1 > stopTimeMS_2
object_name_1 << object_name_2	bool stopTimeMS_1 < stopTimeMS_2

# Print\_conf();

### object\_name.print\_conf ();

If there are multiple breaks during the time period, it shows the total pause time pauseTimeMS, but pauseBeginMS and pauseEndMS only appear for the last pause.

# **Precise timing**

If greater time accuracy is desired, it is recommended to use the Arduino ESP32 and the cadence DELAY\_1MS